GROUND WATER RULE

Infrastructure Finance Conference October 24, 2007

OVERVIEW

- Promulgation
- Sanitary Surveys
- Hydrogeologic Sensitivity Assessment
- Source Water Monitoring
- Treatment Technique Requirements
- Reporting and Recordkeeping
- Special Primacy Requirements (142.16(a)(2) and (o))

RULE DEVELOPMENT BACKGROUND: PUBLIC HEALTH RISKS


• CDC Outbreak Data: 1971–1996

- 318 of 371 outbreaks associated with ground water systems
- Of those 318 microbial outbreaks:
 - 86% were associated with source water
 - 11% were associated with the distribution system
 - 3% were of unknown cause
- Of those involving source water, just under half were systems practicing disinfection

GROUND WATER RULE

- Ground Water Rule Promulgated January 8, 2007.
- Ground Water Rule is effective December 1, 2009.
- The rule apples to all systems that use ground water as a source unless it is combined with surface water (or GWUDI) prior to treatment.
 - This includes consecutive systems receiving finished ground water.
- Will apply to 94% (1,190) systems in New Mexico.

REGULATORY PROVISIONS



HYDROGEOLOGIC SENSITIVITY ASSESSMENT

Purpose

 To identify sensitive sources that will be required to perform routine microbiological monitoring of sources.


Scope

- Non-disinfecting ground water systems
- Frequency
 - One-time assessment

HYDROGEOLOGIC SENSITIVITY ASSESSMENT (continued)

- Two key components of a hydrogeologic assessment:
 - State determines whether a system's wells are located in a sensitive aquifer type (karst, gravel, or fractured bed rock)
 - State determines whether a hydrogeologic barrier is present that protects wells in a sensitive aquifer type
- States may use information collected through the SWAPP for the hydrogeologic sensitivity assessment

REGULATORY PROVISIONS



SOURCE WATER MONITORING

- Two types of source water monitoring requirements:
 - Routine source water monitoring
 - Triggered source water monitoring

ROUTINE SOURCE WATER MONITORING

Purpose

To determine if a sensitive source has fecal contamination

Scope

- Systems that do not provide disinfection.
- Hydrogeologically sensitive sources, as determined by the State.

Frequency

- Monthly for at least one year.
- Begin 1 month after being notified that source is sensitive.
- Sample each source.
- State can eliminate or reduce sampling

TRIGGERED SOURCE WATER MONITORING

Purpose

 To determine if a TC positive sample is caused by source water contamination.

Scope

- Systems that do not treat to 4 log (99.99%) i.e., disinfect
- Frequency
 - Triggered by a total coliform positive sample in the distribution systems (Total Coliform Rule).
 - Must be a valid total coliform result.

Notification

 Water systems must do appropriate public notice. This is Tier 1 Public Notice when a triggered source water sample is positive for a fecal indicator.

TRIGGERED SOURCE WATER MONITORING (cont.)


Sampling

- Must sample source water within 24 hours.
- This includes all sources that could contribute.
- System can identify "representative" sources that serve th affected portion of the distribution system.

Consecutive Systems

- Purchased water systems must notify wholesaler of positive result within 24 hours
- Wholesale systems must conduct source water monitoring within 24 hours for being notified.

REGULATORY PROVISIONS




SANITARY SURVEYS

- Frequency
 - Every 3 years for CWS; 5 years for NCWS
- Eight Elements of a Sanitary Survey To match ESWTR
 - Source
 - Treatment
 - Distribution system integrity
 - Finished water storage
 - Pumps, pump facilities, and control
 - Monitoring, reporting, and data verification
 - Water system management and operations
 - Water system operator compliance with State requirements

SANITARY SURVEYS (continued)

- States must identify significant deficiencies
- State must have corrective action authority
- Systems must fix significant deficiencies or apply treatment

REGULATORY PROVISIONS



REGULATORY PROVISIONS: CORRECTIVE ACTION

Purpose

To protect public health by eliminating or preventing exposure to pathogens

Scope

- A water system must take one of these actions to address a significant deficiency identified during a sanitary survey, or in response to confirmed source water contamination (when one of the follow-up source water samples is positive for a fecal indictor).
- A state may require corrective action be taken in response to an initial fecal indicator positive sample from triggered source water monitoring, triggered monitoring at a wholesale system, or assessment monitoring.

Frequency

Corrective actions must be completed within 120 days or on a State approved schedule

REGULATORY PROVISIONS: CORRECTIVE ACTION (continued)

- Corrective action approaches includes one of the following:
 - Correct the significant deficiency
 - Eliminate the source of contamination
 - Provide an alternative source of water
 - Provide treatment that reliably achieves 4-log inactivation or removal of viruses

CALCULATING INACTIVATION CREDIT

- How is the Inactivation Credit determined?
 - Sampling Required
 - Temperature (°C)
 - pH
 - Disinfectant Residual, in mg/l
 - Peak Hourly Flow, in Gallons/Minute (GPM)
 - Total Volume between point of disinfectant application and the first customer, in gallons

CALCULATING INACTIVATION CREDIT

- How is the Inactivation Credit determined?
 - Obtain Information
 - Determine CT Value
 - Compare CT Value to Appropriate CT Chart
 - Find the Log Inactivation Credit
- CT (mg-min/L) = Concentration of Disinfectant (mg/L)
 X Contact Time (minutes)

TREATMENT TECHNIQUE COMPLIANCE

Log Inactivation			
	2.0	3.0	4.0
pH = 6-9			
Temperature (C)			
0.5	6	9	12
5	4	6	8
10	3	4	6
15	2	3	4
20	1	2	3
25	1	1	2

TREATMENT MONITORING

Purpose

 Ensures reliable disinfection treatment (4-log inactivation or removal of viruses)

Scope

- Systems that notify the State that they currently achieve 4-log inactivation
- Systems that select disinfection as a corrective action

Frequency

- Continuously for systems serving 3,300 or more people
- Daily for systems serving 3,300 or fewer people

REPORTING AND RECORDKEEPING

- Ground water systems conducting compliance monitoring must notify the state by the end of the next business day any time the system fails to meet state-specified requirements for disinfectant residuals, membrane operating criteria, etc.
- Water systems completing corrective action must notify the state within 30 days. The water system must maintain records of:
 - Corrective actions
 - Public Notice
 - Sample invalidation
 - Records related to performance of compliance monitoring

Administrative

- Description of the state authority to require tier 1 public notice in place of tier 2 public notice for GWR violations.
- Demonstration that the state has the authority to require source water monitoring.
- Demonstration that the state has the authority to require corrective action to address significant deficiencies or source water contamination and the authority to require consultation with the state.
- States must also describe how they will implement their sanitary survey program.

Surveys/Treatment

- The state must provide at least one example of a significant deficiency for each of the eight elements and describe how it will determine that a community water system has an outstanding performance record so the frequency of surveys can be extended to 5 years.
- The criteria the state will use when extending the 24 hour time limit for triggered source water monitoring.
- The criteria the state will use to determine that the cause of a total coliform positive sample is directly related to the distribution system so source monitoring is not triggered.
- The criteria the state will use for invalidation of samples.

- Surveys/Treatment (cont.)
 - Criteria for allowing source water monitoring at a location after treatment.
 - Process state will use to determine that a system is achieving 4-log treatment of viruses including what monitoring and compliance requirements the state will require for each type of treatment.
 - The criteria the state will use to determine if a system may discontinue
 4-log treatment of viruses.

- Source Water Monitoring (Sensitivity Assessments)
 - States must decide which viral indicator (E. coli, enterococci, coliphage) they will require.
 - States must determine which systems are high risk and should perform assessment monitoring.
 - States will need to decide what criteria (Hydrogeologic Sensitivity Analysis, source water monitoring history, etc.) they will use to make the high risk determination.
 - States will have to determine the appropriate schedule for each system required to do assessment monitoring and track compliance.